Package 'similaRpeak'

May 30, 2024

Type Package

Title Metrics to estimate a level of similarity between two ChIP-Seq profiles

Version 1.36.0 **Date** 2014-08-08

Description This package calculates metrics which quantify the level of similarity between ChIP-Seq profiles. More specifically, the package implements six pseudometrics specialized in pattern similarity detection in ChIP-Seq profiles.

biocViews BiologicalQuestion, ChIPSeq, Genetics, MultipleComparison, DifferentialExpression

Depends R6 (>= 2.0)

Imports stats

Suggests RUnit, BiocGenerics, knitr, Rsamtools, GenomicAlignments, rtracklayer, rmarkdown, BiocStyle

License Artistic-2.0

URL https://github.com/adeschen/similaRpeak

BugReports https://github.com/adeschen/similaRpeak/issues

VignetteBuilder knitr Encoding UTF-8

NeedsCompilation no

RoxygenNote 6.0.1

git_url https://git.bioconductor.org/packages/similaRpeak

git_branch RELEASE_3_19

git_last_commit 39cd226

git_last_commit_date 2024-04-30

Repository Bioconductor 3.19

Date/Publication 2024-05-29

2 similaRpeak-package

Author Astrid Deschênes [cre, aut].
Elsa Bernatchez [aut],
Charles Joly Beauparlant [aut]
Fabien Claude Lamaze [aut],
Rawane Samb [aut],
Pascal Belleau [aut],
Arnaud Droit [aut]

Maintainer Astrid Deschênes <adeschen@hotmail.com>

Contents

simil	.aRpeak-package	similaR ChIP-S		cs	to	est	ime	ate	a	lev	el	of	sin	nil	ari	ty	be	twe	eer	ı t	wo	
Index																						24
	spearmanCorrMetho	d	 	 	•			•		•		•		•	•		•		•		•	22
	SpearmanCorrelation																					
	similarity		 	 																		18
	RatioNormalizedInte																					
	ratioMaxMaxMethod																					
	ratioIntersectMethod RatioMaxMax																					
	RatioIntersect																					
	ratioAreaMethod .																					
	RatioArea																					
	MetricFactory		 	 																		10
	Metric																					
	diffPosMaxMethod																					
	DiffPosMax																					
	demoProfiles																					
	similaRpeak-package chr7Profiles																					
	similaDmaals maalsaas																					-

Description

This package is calculating six differents metrics to estimate a level of similarity between two ChIP-Seq profiles.

Details

The similarity function calculates six differents metrics:

• RATIO_AREA: The ratio between the areas. The larger value is always divided by the smaller value.

chr7Profiles 3

• DIFF_POS_MAX: The difference between the maximal peaks positions. The difference is always a positive value.

- RATIO_MAX_MAX: The ratio between the maximal peaks values. The larger value is always divided by the smaller value.
- RATIO_INTERSECT: The ratio between the intersection area and the total area.
- RATIO_NORMALIZED_INTERSECT: The ratio between the intersection area and the total area of two normalized profiles. The profiles are normalized by divinding them by their average value.
- SPEARMAN_CORRELATION: The Spearman's rho statistic between profiles.

The function similarity also reports basic information about each ChIP profile such as the number of positions, the area, the maximum value and the position of the maximum value.

To learn more about **similaRpeak** package see: https://github.com/adeschen/similaRpeak/wiki

Author(s)

Astrid Deschenes, Elsa Bernatchez, Charles Joly Beauparlant, Fabien Claude Lamaze, Rawane Samb, Pascal Belleau and Arnaud Droit

Maintainer: Astrid Deschenes <adeschen@hotmail.com>

See Also

- MetricFactory for using a interface to calculate all available metrics separately.
- similarity for calculating all available metrics between two ChIP-Seq profiles.

chr7Profiles	ChIP-Seq profiles of region chr7:61968807-61969730 related to en-
	hancers H3K27ac and H3K4me1 (for demonstration purpose)

Description

ChIP-Seq profiles of region chr7:61968807-61969730 of two histone post-transcriptional modifications linked to highly active enhancers H3K27ac (DCC accession: ENCFF000ASG) and H3K4me1 (DCC accession: ENCFF000ARY) from the Encyclopedia of DNA Elements (ENCODE) data (Dunham I et al. 2012).

Usage

data(chr7Profiles)

4 chr7Profiles

Format

A list with 1 entry. The entry is a list of 2 ChIP-Seq profiles, one per active enhancer (H3K27ac and H3K4me1). The 2 ChIP-Seq profiles are of identical length and specific to a genomic region. Each ChiP-Seq profile is a numerical vector containing the profiles values at each position, as reported in reads per million (RPM).

- chr7Profiles a list containing all demo ChIP-Seq profiles
- chr7Profiles\$chr7.61968807.61969730 a list containing 2 ChIP-Seq profiles for the genomic region chr7:6196880-61969730
- demoProfiles\$chr7.61968807.61969730\$H3K27ac a numeric vector containing the profiles values related to the enhancer H3K27ac, as reported in reads per million (RPM). The first entry of the vector is for position chr7:61968807 while the last entry is for position chr7:61969730
- demoProfiles\$chr7.61968807.61969730\$H3K4me1 a numeric vector containing the profiles values related to the enhancer H3K4me1, as reported in reads per million (RPM). The first entry of the vector is for position chr7:61968807 while the last entry is for position chr7:61969730

Source

The Encyclopedia of DNA Elements (ENCODE) (DCC accession: ENCFF000MZT)

References

• Dunham I, Kundaje A, Aldred SF, et al. An integrated encyclopedia of DNA elements in the human genome. Nature. 2012 Sep 6;489(7414):57-74.

See Also

- demoProfiles ChIP-seq profiles related to enhancers H3K27ac and H3K4me1 (for demonstration purpose)
- MetricFactory for using a interface to calculate all available metrics separately.
- similarity for calculating all available metrics between two ChIP-Seq profiles.

Examples

```
data(chr7Profiles)

## Calculating all metrics for the "chr7.61968807.61969730" region
metrics <- similarity(chr7Profiles$chr7.61968807.61969730$H3K4me1,
chr7Profiles$chr7.61968807.61969730$H3K27ac,
    ratioAreaThreshold=10,
    ratioMaxMaxThreshold=4,
    ratioIntersectThreshold=5,
    ratioNormalizedIntersectThreshold=2,
    diffPosMaxThresholdMinValue=10,
    diffPosMaxThresholdMaxDiff=100,
    diffPosMaxTolerance=0.10)
metrics</pre>
```

demoProfiles 5

You can refer to the vignette to see more examples using ChIP-Seq profiles ## extracted from the Encyclopedia of DNA Elements (ENCODE) data.

demoProfiles

ChIP-Seq profiles of region chr7:61968807-61969730 related to enhancers H3K27ac and H3K4me1 (for demonstration purpose)

Description

ChIP-Seq profiles of region chr7:61968807-61969730 of two histone post-transcriptional modifications linked to highly active enhancers H3K27ac (DCC accession: ENCFF000ASG) and H3K4me1 (DCC accession: ENCFF000ARY) from the Encyclopedia of DNA Elements (ENCODE) data (Dunham I et al. 2012).

Usage

data(demoProfiles)

Format

A list with 1 entry. The entry is a list of 2 ChIP-Seq profiles, one per active enhancer (H3K27ac and H3K4me1). The 2 ChIP-Seq profiles are of identical length and specific to a genomic region. Each ChiP-Seq profile is a numerical vector containing the profiles values at each position, as reported in reads per million (RPM).

- demoProfiles a list containing all demo ChIP-Seq profiles
- demoProfiles\$chr2.70360770.70361098 a list containing 2 ChIP-Seq profiles for the genomic region chr2:70360770-70361098
- demoProfiles\$chr2.70360770.70361098\$H3K27ac a numeric vector containing the profiles values related to the enhancer H3K27ac, as reported in reads per million (RPM). The first entry of the vector is for position chr1:70360770 while the last entry is for position chr2:70361098
- demoProfiles\$chr2.70360770.70361098\$H3K4me1 a numeric vector containing the profiles values related to the enhancer H3K4me1, as reported in reads per million (RPM). The first entry of the vector is for position chr1:70360770 while the last entry is for position chr2:70361098
- demoProfiles\$chr3.73159773.73160145\$H3K4me1 a list containing 2 ChIP-Seq profiles for the genomic region chr3:73159773-73160145
- demoProfiles\$chr3.73159773.73160145\$H3K27ac a numeric vector containing the profiles values related to the enhancer H3K27ac, as reported in reads per million (RPM). The first entry of the vector is for position chr2:73159773 while the last entry is for position chr3:73160145
- demoProfiles\$chr3.73159773.73160145\$H3K4me1 a numeric vector containing the profiles values related to the enhancer H3K4me1, as reported in reads per million (RPM). The first entry of the vector is for position chr3:73159773 while the last entry is for position chr3:73160145

6 DiffPosMax

Source

The Encyclopedia of DNA Elements (ENCODE) (DCC accession: ENCFF000MZT)

References

• Dunham I, Kundaje A, Aldred SF, et al. An integrated encyclopedia of DNA elements in the human genome. Nature. 2012 Sep 6;489(7414):57-74.

See Also

- chr7Profiles ChIP-Seq profiles of region chr7:61968807-61969730 related to enhancers H3K27ac and H3K4me1 (for demonstration purpose)
- MetricFactory for using a interface to calculate all available metrics separately.
- similarity for calculating all available metrics between two ChIP-Seq profiles.

Examples

DiffPosMax

DiffPosMax class

Description

An object which is a interface to calculate he difference of profiles maximal peaks positions.

The DiffPosMax object is needed to calculate the difference of profiles maximal peaks positions. A threshold and the two profiles are set during the DiffPosMax object creation. If different thresholds or profiles are needed, the calculateMetric function should be used, with the new profiles and thresholds passed as arguments to update those values inside the DiffPosMax object.

The threshold is the minimum peak value accepted to calculate the ratio.

The thresholdDiff is the maximum distance accepted between two maximum peaks positions in the same profile. When the thresholdDiff is not respected, the profile is considered having more than one peak.

The tolerance is the maximum variation accepted on the maximum peak value to consider a position as a peak position. The tolerance must be between 0 and 1. All peaks within the tolerated range will be considered in the calculation of the metric.

DiffPosMax 7

Usage

DiffPosMax

Format

An object of class R6ClassGenerator of length 24.

Value

The DiffPosMax\$new function returns a DiffPosMax object which contains the information about the two profiles and the thresholds used to calculate the metric. It can be used, as many times needed, to calculate the specified metric.

Constructor

Create a DiffPosMax object.

DiffPosMax\$new(profile1, profile2, threshold = 1, thresholdDiff = 100, tolerance = 0.01)

The threshold is the minimum peak value accepted to calculate the ratio.

The thresholdDiff is the maximum distance accepted between two maximum peaks positions in the same profile. When the thresholdDiff is not respected, the profile is considered having more than one peak.

The tolerance is the maximum variation accepted on the maximum peak value to consider a position as a peak position. All peaks within the tolerated range will be considered in the calculation of the metric. The tolerance must

The DiffPosMax object inherites those functions:

- getMetric A function that returns the value of the calculated metric
- getInfo A function that returns a description of the metric with the metric value.
- getType A function that returns the unique name associated to this metric
- calculateMetric A function that modifies the values of the two profiles and the threshold.
 The new values (profile1, profile2, threshold, thresholdDiff, tolerance) are passed as arguments.

Author(s)

Astrid Deschenes

See Also

• MetricFactory for using a interface to calculate all available metrics separately or togheter.

8 diffPosMaxMethod

diffPosMaxMethod	Difference between two profiles maximal peaks positions	

Description

Calculate and return the difference between two profiles maximal peaks positions. The difference is always the first profile value (profile1 parameter) minus the second profile value (profile2 parameter). When more than one maximual peak is present in one profile, the mediane of the position is calculated and used as the maximal peak position. If one threshold is not respected, the function returns NA.

Usage

```
diffPosMaxMethod(profile1, profile2, threshold = 1, thresholdDist = 100,
  tolerance = 0.01)
```

Arguments

profile1	a vector of numeric values, the first profile containing the alignment depth for each position. The profile1 and profile2 should have the same length.
profile2	a vector of numeric values, the second profile containing the alignment depth for each position. The profile1 and profile2 should have the same length.
threshold	a numeric, the minimum peak value accepted to calculate the metric. Default $=$ 1.
thresholdDist	a numeric, the maximum distance accepted between two maximum peaks positions in the same profile. Default = 100 .
tolerance	a numeric, the maximum variation accepted on the maximum value to consider a position as a peak position. The tolerance must

Value

The calculated ratio or NA if not all thresholds are respected.

Author(s)

Astrid Deschenes, Elsa Bernatchez

See Also

• MetricFactory for using the recommanded interface to calculate all available metrics separately or togheter.

Metric 9

Metric Metric class

Description

A class which represents a abstract Metric object which is used to quantify the similarity between two profiles covering the same range.

The Metric class should not be directly instanciated. It should be used as the parent class of a specific metric class.

Usage

Metric

Format

An object of class R6ClassGenerator of length 24.

Value

The Metric\$new function returns a Metric object which contains the information about the two profiles and the threshold used to calculate the metric. It can be used, as many times needed, to calculate the specified metric.

Constructor

Create a Metric object.

Metric\$new(profile1, profile2, threshold = NULL)

The Metric object inherites those functions:

- getMetric A function that returns the value of the calculated metric
- getInfo A function that returns a description of the metric with the metric value.
- getType A function that returns the unique name associated to this metric
- calculateMetric A function that modifies the values of the two profiles and the threshold. The new values (profile1, profile2, threshold) are passed as arguments.

Author(s)

Astrid Deschenes

See Also

MetricFactory for using the recommanded interface to calculate all available metrics separately or togheter.

10 MetricFactory

MetricFactory

MetricFactory object

Description

An object which is a interface to calculate all available metrics separately.

The MetricFactory object is inspired from the factory design pattern. Only one instance of MetricFactory object is necessary to calculate all available metrics for different profiles, as long as the thresholds set in the MetricFactory instance are appropriate for the calculation. The thresholds are set during the MetricFactory object creation and cannot be changed afterwards. If different thresholds are needed, a new MetricFactory object, with the new thresholds, must be instantiated.

Usage

MetricFactory

Format

An object of class R6ClassGenerator of length 24.

Value

The MetricFactory\$new function returns a MetricFactory object which contains the information about the thresholds used to calculate each metric. It can be used, as many times needed, to calculate the specified metrics.

Constructor

Create a MetricFactory object.

MetricFactory\$new(ratioAreaThreshold=1, ratioMaxMaxThreshold=1, ratioIntersectThreshold=1, ratioNormalizedIntersectThreshold=1, diffPosMaxThresholdMinValue=1, diffPosMaxThresholdMaxDiff=100, diffPosMaxTolerance=0.01, spearmanCorrSDThreashold=1e-8)

- ratioAreaThreshold The minimum denominator accepted to calculate the ratio of the area between both profiles. Default = 1.
- ratioMaxMaxThreshold The minimum denominator accepted to calculate the ratio of the maximum values between both profiles. Default = 1.
- ratioIntersectThreshold The minimum denominator accepted to calculate the ratio of the intersection area of both profiles and the total area. Default = 1.
- ratioIntersectThreshold The minimum denominator accepted to calculate the ratio of the intersection area of both profiles and the total area for normalized profiles. Default = 1.
- diffPosMaxThresholdMinValue The minimum peak accepted to calculate the metric. Default = 1.
- diffPosMaxThresholdMaxDiff The maximum distance accepted between 2 peaks positions in one profile to calculate the metric. Default=100.

MetricFactory 11

• diffPosMaxTolerance The maximum variation accepted on the maximum value to consider a position as a peak position. Default=0.01.

• spearmanCorrSDThreashold The minimum standard deviation accepted on both profiles to consider to calculate the metric. Default=1e-8.

Author(s)

Astrid Deschenes

See Also

- similarity for calculating all available metrics between two ChIP-Seq profiles.
- demoProfiles for more informations about ChIP-Seq profiles present in the demoProfiles data.

Examples

```
## Initialized the factory object
factory = MetricFactory$new(ratioAreaThreshold=100,
    ratioIntersectThreshold=20,
    diffPosMaxTolerance=0.04)
## Define 2 ChIP-Seq profiles
profile1 <- c(1,59,6,24,65,34,15,4,53,22)
profile2 <- c(15,9,46,44,9,39,27,34,34,4)
## Use the factory object to calculate each metric separatly
ratio_max_max <- factory$createMetric(metricType="RATIO_MAX_MAX",
    profile1, profile2)
ratio_max_max
diff_pos_max <- factory$createMetric(metric="DIFF_POS_MAX", profile1,</pre>
    profile2)
diff_pos_max
## Example using ChIP-Seq profiles of H3K27ac (DCC accession: ENCFF000ASG)
## and H3K4me1 (DCC accession: ENCFF000ARY) from the Encyclopedia of DNA
## Elements (ENCODE) for the region
data(demoProfiles)
## Visualize ChIP-Seq profiles
plot(demoProfiles$chr3.73159773.73160145$H3K27ac, type="l", col="blue",
    xlab="", ylab="", ylim=c(0, 125), main="chr3:73159773-73160145")
par(new=TRUE)
plot(demoProfiles$chr3.73159773.73160145$H3K4me1, type="1", col="darkgreen",
    xlab="Position", ylab="Coverage in reads per million (RPM)",
    ylim=c(0, 125))
legend("topright", c("H3K27ac","H3K4me1"), cex=1.2,
    col=c("blue","darkgreen"), lty=1)
## Calculate metrics using factory object
```

12 RatioArea

```
ratio_norm_intersect <- factory$createMetric(metricType =
   "RATIO_NORMALIZED_INTERSECT",
   profile1=demoProfiles$chr3.73159773.73160145$H3K4me1,
   profile2=demoProfiles$chr3.73159773.73160145$H3K27ac)
ratio_norm_intersect

ratio_area <- factory$createMetric(metricType="RATIO_AREA",
   profile1=demoProfiles$chr3.73159773.73160145$H3K4me1,
   profile2=demoProfiles$chr3.73159773.73160145$H3K27ac)
ratio_area</pre>
```

RatioArea

RatioArea class

Description

An object which is a interface to calculate ratio between the profile area of two profiles.

The RatioArea object is needed to calculate the ratio between the profile area of two profile. A threshold and the two profiles are set during the RatioArea object creation. If different threshold or profiles are needed, the calculateMetric function should be used, with the new profiles and threshold passed as arguments to update those values inside the RatioArea object.

The threshold is the minimum profile area value accepted to calculate the ratio.

Usage

RatioArea

Format

An object of class R6ClassGenerator of length 24.

Value

The RatioArea\$new function returns a RatioArea object which contains the information about the two profiles and the threshold used to calculate the metric. It can be used, as many times needed, to calculate the specified metric.

Constructor

Create a RatioArea object.

RatioArea\$new(profile1, profile2, threshold = 1)

The threshold is the minimum profile area value accepted to calculate the ratio.

The RatioArea object inherites those functions:

- getMetric A function that returns the value of the calculated metric
- getInfo A function that returns a description of the metric with the metric value.

ratioAreaMethod 13

- getType A function that returns the unique name associated to this metric
- calculateMetric A function that modifies the values of the two profiles and the threshold. The new values (profile1, profile2, threshold) are passed as arguments.

Author(s)

Astrid Deschenes

See Also

• MetricFactory for using a interface to calculate all available metrics separately or togheter.

ratioAreaMethod	Ratio of profiles area between two profiles

Description

Calculate and return the ratio of profiles area between two profiles covering the same range. The area of the first profile is always divided by the area of the second profile. If one area value is inferior to the threshold, the function returns NA.

Usage

```
ratioAreaMethod(profile1, profile2, threshold = 1)
```

Arguments

profile1	a vector of numeric values, the first profile containing the alignment depth for each position. The profile1 and profile2 should have the same length.
profile2	a vector of numeric values, the second profile containing the alignment depth for each position. The profile1 and profile2 should have the same length.
threshold	a numeric, the minimum profile area value accepted to calculate a ratio.

Value

The calculated ratio or NA if one profile area value is inferior to the threshold.

Author(s)

Astrid Deschenes, Elsa Bernatchez

See Also

• MetricFactory for using the recommanded interface to calculate all available metrics separately or togheter.

14 RatioIntersect

RatioIntersect

RatioIntersect class

Description

An object which is a interface to calculate the ratio between the peaks values between two profiles.

The RatioIntersect object is needed to calculate the ratio of profiles intersection area between two profiles and those profiles total areas. A threshold and the two profiles are set during the RatioIntersect object creation. If different threshold or profiles are needed, the calculateMetric function should be used, with the new profiles and threshold passed as arguments to update those values inside the RatioIntersect object.

The threshold is the minimum total area value accepted to calculate a ratio.

Usage

RatioIntersect

Format

An object of class R6ClassGenerator of length 24.

Value

The RatioIntersect\$new function returns a RatioIntersect object which contains the information about the two profiles and the threshold used to calculate the metric. It can be used, as many times needed, to calculate the specified metric.

Constructor

Create a RatioIntersect object.

RatioIntersect\$new(profile1, profile2, threshold = 1)

The threshold is the minimum total area value accepted to calculate a ratio.

The RatioIntersect object inherites those functions:

- getMetric A function that returns the value of the calculated metric
- getInfo A function that returns a description of the metric with the metric value.
- getType A function that returns the unique name associated to this metric
- calculateMetric A function that modifies the values of the two profiles and the threshold. The new values (profile1, profile2, threshold) are passed as arguments.

Author(s)

Astrid Deschenes

See Also

• MetricFactory for using a interface to calculate all available metrics separately or togheter.

ratioIntersectMethod 15

ratioIntersectMethod	Ratio between the intersection area of two profiles and the total area covered by those profiles
	covered by mose projues

Description

Calculate and return the ratio between the intersection area of two profiles and the total area covered by those profiles. If the total area is inferior to the threshold, the function returns NA.

Usage

```
ratioIntersectMethod(profile1, profile2, threshold = 1)
```

Arguments

profile1	a vector of numeric values, the first profile containing the alignment depth for each position. The profile1 and profile2 should have the same length.
profile2	a vector of numeric values, the second profile containing the alignment depth for each position. The profile1 and profile2 should have the same length.
threshold	a numeric, the minimum total area value accepted to calculate a ratio.

Value

The calculated ratio or NA if the total area is inferior to the threshold.

Author(s)

Astrid Deschenes, Elsa Bernatchez

See Also

• MetricFactory for using the recommanded interface to calculate all available metrics separately or togheter.

RatioMaxMax	RatioMaxMax class

Description

An object which is a interface to calculate the ratio between the peaks values between two profiles.

The RatioMaxMax object is needed to calculate the ratio between the peaks values between two profiles. A threshold and the two profiles are set during the RatioMaxMax object creation. If different threshold or profiles are needed, the calculateMetric function should be used, with the new profiles and threshold passed as arguments to update those values inside the RatioMaxMax object.

The threshold is the minimum peak value accepted to calculate a ratio.

16 ratioMaxMaxMethod

Usage

RatioMaxMax

Format

An object of class R6ClassGenerator of length 24.

Value

The RatioMaxMax\$new function returns a RatioMaxMax object which contains the information about the two profiles and the threshold used to calculate the metric. It can be used, as many times needed, to calculate the specified metric.

Constructor

Create a RatioMaxMax object.

RatioMaxMax\$new(profile1, profile2, threshold = 1)

The threshold is the minimum peak value accepted to calculate a ratio.

The RatioMaxMax object inherites those functions:

- getMetric A function that returns the value of the calculated metric
- getInfo A function that returns a description of the metric with the metric value.
- getType A function that returns the unique name associated to this metric
- calculateMetric A function that modifies the values of the two profiles and the threshold. The new values (profile1, profile2, threshold) are passed as arguments.

Author(s)

Astrid Deschenes

See Also

• MetricFactory for using a interface to calculate all available metrics separately or togheter.

ratioMaxMaxMethod

Ratio of profiles maximal peaks between two profiles

Description

Calculate and return the ratio of profiles maximal peaks between two profiles covering the same range. The maximal peak of the first profile is always divided by the maximal peak of the second profile. If one peak value is inferior to the threshold, the function returns NA.

Usage

```
ratioMaxMaxMethod(profile1, profile2, threshold = 1)
```

RatioNormalizedIntersect 17

Arguments

profile1 a vector of numeric values, the first profile containing the alignment depth for

each position. The profile1 and profile2 should have the same length.

profile2 a vector of numeric values, the second profile containing the alignment depth

for each position. The profile1 and profile2 should have the same length.

threshold a numeric, the minimum peak value accepted to calculate a ratio.

Value

The calculated ratio or NA if one peak value is inferior to the threshold.

Author(s)

Astrid Deschenes, Elsa Bernatchez

See Also

• MetricFactory for using the recommanded interface to calculate all available metrics separately or togheter.

RatioNormalizedIntersect

RatioNormalizedIntersect class

Description

An object which is a interface to calculate the ratio of profiles intersection area between two normalized profiles. The profiles are

The RatioNormalizedIntersect object is needed to calculate the ratio of profiles intersection area between two normalized profiles. A threshold and the two profiles are set during the RatioNormalizedIntersect object creation. If different profiles are needed, the calculateMetric function should be used, with the new profiles passed as arguments to update those values inside the RatioNormalizedIntersect object.

The threshold is the minimum total normalized area value accepted to calculate a ratio.

Usage

RatioNormalizedIntersect

Format

An object of class R6ClassGenerator of length 24.

18 similarity

Value

The RatioNormalizedIntersect\$new function returns a RatioNormalizedIntersect object which contains the information about the two profiles. It can be used, as many times needed, to calculate the specified metric.

Constructor

Create a RatioNormalizedIntersect object.

```
RatioNormalizedIntersect$new(profile1, profile2, threshold = 1)
```

The threshold is the minimum total normalized area value accepted to calculate a ratio. Default = 1 The RatioNormalizedIntersect object inherites those functions:

- getMetric A function that returns the value of the calculated metric
- getInfo A function that returns a description of the metric with the metric value.
- getType A function that returns the unique name associated to this metric
- calculateMetric A function that modifies the values of the two profiles and the threshold. The new values (profile1, profile2, threshold) are passed as arguments.

Author(s)

Astrid Deschenes

See Also

• MetricFactory for using a interface to calculate all available metrics separately or togheter.

similarity Calculate metrics ChIP-Seq profiles	which estimate the level of similarity between two
---	--

Description

It returns a list containing information about both ChIP-Seq profiles and a list of all similarity metrics: the ratio of the maximum values, the ratio of the areas, the ratio between the intersection area and the total area (for normalized and non-normalized profiles), the difference between two profiles maximal peaks positions and the Spearman's rho statistic.

Usage

```
similarity(profile1, profile2, ratioAreaThreshold = 1,
  ratioMaxMaxThreshold = 1, ratioIntersectThreshold = 1,
  ratioNormalizedIntersectThreshold = 1, diffPosMaxThresholdMinValue = 1,
  diffPosMaxThresholdMaxDiff = 100, diffPosMaxTolerance = 0.01,
  spearmanCorrSDThreashold = 1e-08)
```

similarity 19

Arguments

profile1 Vector containing the RPM values of the first ChIP-Seq profile for each position

of the selected region.

profile2 Vector containing the RPM values of the second ChIP-Seq profile for each po-

sition of the selected region.

ratioAreaThreshold

The minimum denominator accepted to calculate the ratio of the area between both profiles. The value has to be positive. Default = 1.

ratioMaxMaxThreshold

The minimum denominator accepted to calculate the ratio of the maximal peaks values between both profiles. The value has to be positive. Default = 1.

ratioIntersectThreshold

The minimum denominator accepted to calculate the ratio of the intersection area of both profiles over the total area. The value has to be positive. Default = 1.

ratioNormalizedIntersectThreshold

The minimum denominator accepted to calculate the ratio of the intersection area of both normalized profiles over the total area. The value has to be positive. Default = 1.

diffPosMaxThresholdMinValue

The minimum peak accepted to calculate the metric. The value has to be positive. Default = 1.

diffPosMaxThresholdMaxDiff

The maximum distance accepted between 2 peaks positions in one profile to calculate the metric. The value has to be positive. Default=100.

diffPosMaxTolerance

The maximum of variation accepted on the maximum value to consider a position as a peak position. The value can be between 0 and 1. Default=0.01.

spearmanCorrSDThreashold

The minimum standard deviation accepted on both profiles to calculate the metric. Default=1e-8.

Details

similarity uses the two vectors passed as arguments to calculate the metrics. When the metric is a ratio, it always verify that the threshold for the denominator is respected. If the threshold is not respected, the metric is assigned the NA value.

Value

A list containing:

- nbrPosition The number of positions included in each profile.
- areaProfile1 The area of the first profile.
- areaProfile2 The area of the second profile.
- maxProfile1 The maximum value in the first profile.

20 similarity

- maxProfile2 The maximum value in the second profile.
- maxPositionProfile1 The list of positions of the maximum value in the first profile.
- maxPositionProfile2 The list of positions of the maximum value in the second profile.
- metrics A list with thefollowing items:
 - RATIO_AREA The ratio between the areas. The larger value is always divided by the smaller value.NA if minimal threshold is not respected.
 - DIFF_POS_MAX The difference between the maximal peaks positions. The difference is always the first profile value minus the second profile value. NA is returned if minimal peak value is not respected. A profile can have more than one position with the maximum value. In that case, the median position is used. A threshold argument can be set to consider all positions within a certain range of the maximum value. A threshold argument can also be set to ensure that the distance between two maximum values is not too wide. When this distance is not respected, it is assumed that more than one peak is present in the profile and NA is returned.
 - RATIO_MAX_MAX The ratio between the maximal peaks values. The first profile is always
 divided by the second profile. NA if minimal threshold is not respected.
 - RATIO_INTERSECT The ratio between the intersection area and the total area. NA if minimal threshold is not respected.
 - RATIO_NORMALIZED_INTERSECT The ratio between the intersection area and the total area of normalized profiles. NA if minimal threshold is not respected.
 - SPEARMAN_CORRELATION The Spearman's rho statistic between profiles. NA if minimal threshold is not respected or when no complete element pair is present between both profiles.

Author(s)

Astrid Deschenes, Elsa Bernatchez

See Also

- MetricFactory for using a interface to calculate all available metrics separately or togheter.
- demoProfiles for more informations about ChIP-Seq profiles present in the demoProfiles data.

Examples

```
## Defining two CHiP-Seq profiles
profile1<-c(3,59,6,24,65,34,15,4,53,22,21,12,11)
profile2<-c(15,9,46,44,9,39,27,34,34,4,3,4,2)

## Example usign default thresholds
similarity(profile1, profile2)

## Example using customised thresholds
similarity(profile1, profile2,
    ratioAreaThreshold=5,
    ratioMaxMaxThreshold=12,</pre>
```

SpearmanCorrelation 21

```
ratioNormalizedIntersectThreshold=2.2,
   diffPosMaxThresholdMinValue=2,
   diffPosMaxThresholdMaxDiff=130,
   diffPosMaxTolerance=0.03,
    spearmanCorrSDThreashold=1e-3)
## Example using ChIP-Seq profiles of H3K27ac (DCC accession: ENCFF000ASG)
## and H3K4me1 (DCC accession: ENCFF000ARY) from the Encyclopedia of DNA
## Elements (ENCODE) for the region
data(demoProfiles)
## Visualize ChIP-Seq profiles
plot(demoProfiles$chr2.70360770.70361098$H3K27ac,
    type="1", col="blue", xlab="", ylab="", ylim=c(0, 25),
    main="chr2:70360770-70361098")
par(new=TRUE)
plot(demoProfiles$chr2.70360770.70361098$H3K4me1,
    type="l", col="darkgreen", xlab="Position",
   ylab="Coverage in reads per million (RPM)", ylim=c(0, 25))
legend("topright", c("H3K27ac","H3K4me1"), cex=1.2,
   col=c("blue","darkgreen"), lty=1)
# Calculate metrics
similarity(demoProfiles$chr2.70360770.70361098$H3K4me1,
   demoProfiles$chr2.70360770.70361098$H3K27ac,
   ratioAreaThreshold=15,
    ratioMaxMaxThreshold=5,
    ratioIntersectThreshold=12,
   ratioNormalizedIntersectThreshold=2.2,
   diffPosMaxThresholdMinValue=2,
   diffPosMaxThresholdMaxDiff=130,
   diffPosMaxTolerance=0.03,
    spearmanCorrSDThreashold=0.1)
## You can refer to the vignette to see more examples using ChIP-Seq profiles
## extracted from the Encyclopedia of DNA Elements (ENCODE) data.
```

SpearmanCorrelation Spearma

SpearmanCorrelation class

Description

An object which is a interface to calculate the Spearman's

The SpearmanCorrelation object is needed to calculate the ratio between the peaks values between two profiles. A threshold and the two profiles are set during the SpearmanCorrelation object creation. If different threshold or profiles are needed, the calculateMetric function should be used, with the new profiles and threshold passed as arguments to update those values inside the SpearmanCorrelation object.

The threshold is the minimum standard deviation of the profile accepted to calculate a ratio.

22 spearmanCorrMethod

Usage

SpearmanCorrelation

Format

An object of class R6ClassGenerator of length 24.

Value

The SpearmanCorrelation\$new function returns a SpearmanCorrelation object which contains the information about the two profiles. It can be used, as many times needed, to calculate the specified metric.

Constructor

Create a SpearmanCorrelation object.

SpearmanCorrelation\$new(profile1, profile2, threshold = 1e-8)

The threshold is the minimum standard deviation of the profile accepted to calculate a ratio. Default = 1e-8

The SpearmanCorrelation object inherites those functions:

- getMetric A function that returns the value of the calculated metric
- getInfo A function that returns a description of the metric with the metric value.
- getType A function that returns the unique name associated to this metric
- calculateMetric A function that modifies the values of the two profiles and the threshold. The new values (profile1, profile2) are passed as arguments.

Author(s)

Astrid Deschenes

See Also

• MetricFactory for using a interface to calculate all available metrics separately or togheter.

 ${\tt spearmanCorrMethod}$

Spearman's rho statistic of two profiles

Description

Calculate and return the Spearman's rho statistic of two profiles. If one profile has a standard deviation inferior to the threshold, the function returns NA. When no complete element pair are present, NA is returned.

Usage

```
spearmanCorrMethod(profile1, profile2, threshold = 1e-08)
```

spearmanCorrMethod 23

Arguments

profile1	a vector of numeric values, the first profile containing the alignment depth for each position. The profile1 and profile2 should have the same length.
profile2	a vector of numeric values, the second profile containing the alignment depth for each position. The profile1 and profile2 should have the same length.
threshold	a numeric, the minimum standard deviation accepted to calculate a ratio. Default = 1e-8

Value

The calculated ratio or NA if one profile has a standard deviation inferior to the threshold. If profiles have no complete element pair, NA is returned.

Author(s)

Astrid Deschenes, Elsa Bernatchez

See Also

• MetricFactory for using the recommanded interface to calculate all available metrics separately or togheter.

Index

```
* datasets
    chr7Profiles, 3
    demoProfiles, 5
    DiffPosMax, 6
    Metric, 9
    MetricFactory, 10
    RatioArea, 12
    RatioIntersect, 14
    RatioMaxMax, 15
    RatioNormalizedIntersect, 17
    SpearmanCorrelation, 21
* package
    similaRpeak-package, 2
chr7Profiles, 3, 6
demoProfiles, 4, 5, 11, 20
DiffPosMax, 6
diffPosMaxMethod, 8
Metric, 9
MetricFactory, 3, 4, 6-9, 10, 13-18, 20, 22,
        23
RatioArea, 12
ratioAreaMethod, 13
RatioIntersect, 14
ratioIntersectMethod, 15
RatioMaxMax, 15
ratioMaxMaxMethod, 16
RatioNormalizedIntersect, 17
similarity, 2-4, 6, 11, 18
similaRpeak (similaRpeak-package), 2
similaRpeak-package, 2
{\tt SpearmanCorrelation}, {\tt 21}
spearmanCorrMethod, 22
```